

Harmony Commands	Shield Recognized Commands	Kodi Recognized Commands	Keymap Editor ID#
A	-	-	-
B	-	-	-
BACK	Back	Back	61448
CHANNELDOWN	-	-	-
CHANNELUP	-	-	-
DELETE	-	Delete	61575
DIRECTIONDOWN	Down	Down	61579
DIRECTIONLEFT	Left	Left	61570
DIRECTIONRIGHT	Right	Right	61571
DIRECTIONUP	Up	Up	61568
ENTER	Enter	Enter	61453
ESCAPE	Escape	Escape	61467
FASTFORWARD	Fastforward	Fastforward	61637
GAS	-	-	-
HIDDIRECTIONDOWN	Down	Down	61579
HIDDIRECTIONLEFT	Left	Left	61570
HIDDIRECTIONRIGHT	Right	Right	61571
HIDDIRECTIONUP	Up	Up	61568
HOME	Home	Can't use	-
LANGUAGE	-	-	-
LEFTBUMP	-	-	-
LEFTTRIGGER	-	-	-
MENU	?	Menu	61656
MUTE	Mute	Can't Use	-
OK	Select	Select	61453
PAGEDOWN	?	Page down	61573
PAGEUP	?	Page up	61572
PAUSE	Play/Pause	Play/Pause	61628
PLAY	Play/Pause	Play/Pause	61628
POWEROFF	Power off	Can't Use	-
POWERON	Power on	Can't Use	-
POWERTOGGLE	Power Toggle	Can't Use	-
RETURN	Return	Return	61448
REWIND	Rewind	Rewind	61636
RIGHTBUMPER	-	-	-
RIGHTTRIGGER	-	-	-
SHIELD	-	-	-
SKIPBACK	Skip Back	Skip Back	61627
SKIPFORWARD	Skip Forward	Skip Forward	61626
STOP	Stop	Stop	61628
VOLUMEUP	Volume Up	Can't Use	-
VOLUMEDOWN	Volume Down	Can't Use	-
X	-	-	-
Y	-	-	-
0	-	-	-
1	-	-	-
2	-	-	-
3	-	-	-
4	-	-	-
5	-	-	-
6	-	-	-
7	-	-	-
8	-	-	-
9	-	-	-